

Nepali Indic Input 2 - User Guide

Contents

WHAT IS NEPALI INDIC INPUT 2?	3
SYSTEM REQUIREMENTS.....	3
TO INSTALL NEPALI INDIC INPUT 2.....	3
TO USE NEPALI INDIC INPUT 2.....	4
SUPPORTED KEYBOARDS.....	5
NEPALI TRANSLITERATION.....	5
<i>Keyboard Rules</i>	5
NEPALI INSCRIPT	8
NEPALI TYPEWRITER.....	9
<i>Keyboard Rules</i>	9
TOOL SETTING OPTIONS	12
ON-THE-FLY HELP	12
SHOW KEYBOARD	12
SWITCH TO ENGLISH/NEPALI	13
HELP	13
TROUBLESHOOTING	14
TO UNINSTALL NEPALI INDIC INPUT 2.....	15

What is Nepali Indic Input 2?

Nepali Indic Input 2 provides a very convenient way of entering text in Nepali Language using the English QWERTY keyboard in any editing application (Office Application/WordPad /Notepad) that supports Text Services. Nepali Indic Input 2 tool will be packaged as a setup and running the setup will invoke the services. The tool supports all popular keyboard layouts.

System Requirements

Windows Vista

Windows 7

*Tool is compatible with equivalent 64-bit Operating Systems mentioned above.

To Install Nepali Indic Input 2

Installation of the Nepali Indic Input 2 is a very easy process that takes less than two minute to complete.

Run or double click **Nepali Indic Input 2** Setup. The setup wizard will guide you through the installation process. Once the installation process is complete, **Nepali Indic Input 2 has been successfully installed** will be displayed.

Note: On Windows Vista and Windows 7, if your user login does not have administrative privileges or is not included in the user group of administrators right click the "Setup.exe" icon and select "Run as Administrator".

To Use Nepali Indic Input 2

1. Start any Office application, including WordPad or Notepad.
2. Click the Language Indicator located in the System Tray on the right side of the Windows taskbar or on Language bar as shown below. Select **NE-Nepali (Nepal)** for Windows 7/ Vista.



3. Select **Nepali Indic Input 2** from the shortcut menu that appears. The PC is now ready to start typing in Nepali.



Note: If you are unable to view Language bar on your PC [Click Here](#).

Supported Keyboards

Nepali Indic Input 2 supports various types of Keyboards. Click **Settings** Icon and select **Keyboard**. Choose keyboard layout of your choice from list of available keyboards.



Nepali Transliteration

User can type his message in Roman using the Standard English keyboard, which is transliterated on-the-fly to Nepali. It works on the logic of phonetics and is most effective when user write the word the way it is spoken.

Keyboard Rules

Vyanjan (Consonants)									
क	ka, ca,qa	ख	kha	ग	ga	घ	gha	ङ	Nga
च	cha	छ	chha	ज	ja	झ	jha	ञ	Nja
ट	Ta	ठ	Tha	ડ	Da	ঢ	Dha	ণ	Na
ত	ta	থ	tha	দ	da	ধ	dha	ন	na
প	pa	ফ	pha,fa	ব	ba	ভ	bha	ম	ma
য	ya	ৰ	ra	ল	la	ৱ	va,wa	শ	sha
ষ	Sha	স	sa	হ	ha	ঃ	kSha,Xa	ঢ	Tra
ঞ	Gya,jNja,dnya								

Swar (Vowels)									
অ	a	আ	aa	ই	i	ই	ee,ii,I	ঁ	u
ঔ	oo,uu,U	ঔ	R	এ	e	ঁ	A	ঁ	ai,ei
ঁ	o	ঁ	O	ঁ	au,ou	ঁ	a^	ঁ:	aH

Examples	
Input	Output
ekanaashako	एकनाशको
chauDaaii	चौडाई

Matras											
া	aa	ি	i	ী	ee,ii,I	ও	u	়	০০,ুু,O	়	R
ে	e	়	ai,ei	ো	o	়ী	au,ou	়ু	A	়ো	O

Examples	
Input	Output
najik	নজিক
seemaana	সীমানা

Anuswara, Visarga and Chandrabindi					
ঁ	ঁ	ঃ	H	ঁ	M

Examples	
Input	Output
Janasa^khyaa	জনসংখ্যা
praShThaH	পৃষ্ঠ:
nayaam	নয়াঁ

Conjuncts									
ক্ৰ	kr	প্ৰ	pr	ক়ত	qt	ক্ৰ	kt	ন্ম	nm
ঘ	dy	ছ	ddh	ছ	dw	ক্স	ks,x	ঁ	rp

Examples	
Input	Output
sangharSh	সংঘৰ্ষ
shreNiikaraN	শ্ৰেণীকৰণ

Nukta Consonants									
ক়	qa	খ	Kha	গ়	Ga	়	za	ঁ	D_a
ঁ	Fa	ঁ	Dh_a						


Example:	
Input	Output
waFaa	वफा
paDh_aaee	पढाई

Explicit Halant Example:	
Input	Output
pardachhan_	पर्दछन्
maan~dachhan_	मान्दछन्

Explicit Half Consonants Example:	
Input	Output
mush~kilale	मुश्किले
vish~v	विश्व

Special Rules	
If capital 'M' or capital 'H' or caret '^' appear after conso, vowel or matra map them to 'chandrabindi', 'visarga' or 'anuswar'. Exceptional case: If capital 'M' or capital 'H' come at the start of a word it should be interpreted as small case 'm' and 'h'.	
If 'R' is followed by 'i', 'a' or 'u', ignore matra as 'R' stands for Ra(Rishi).	RiShi (ऋषि)
If 'n' is followed by a consonant, replace it with anuswar. Exceptional cases: 'ny' ("n" followed by y), nm ("n" followed by "m") and nn (na followed by na).	khaadyaann (खाद्यान्न)
If 'm' is followed by a consonant, replace it with anuswar. Exceptional cases: 'my' (ma followed by ya), mm (ma followed by ma) and mm (ma followed by na).	
Character '_' (underscore) can be used to generate explicit half consonants and preventing the formation of conjuncts.	
Words ending with a consonant and "a" will be treated as ending with "aa" matra. An exception to this rule is conjuncts appearing at the end of the word with an "a".	
To type Roman Numerals (Numbers), use the Numpad Keys of the Keyboard with Caps Lock Key ON.	1,2,3,...,9,0.
To type Lingual Numerals (Numbers), use the Numpad Keys of the Keyboard with Caps Lock Key OFF.	੧,੨,੩,੪,੫,੬,੭,੮,੯,੦


Nepali Inscript



Special Rules

consoA + halant(d) + consoB = conjunct	क + ् + त = क्त
consoA + halant(d) + Ctrl+Shift+1 + consoB = half consoA + full consoB	क + ् + CtrlShift 1+ त = क्ता
consoA + halant(d) + Ctrl+Shift+2 + consoB = disjoint conjunct	क ् + CtrlShift 2+ त = क्त
To type Roman Numerals (Numbers), use the Numpad Keys of the Keyboard with Caps Lock Key ON.	1, 2, 3,...,9, 0.
To type Lingual Numerals (Numbers), use the Numpad Keys of the Keyboard with Caps Lock Key OFF.	१,२,३,४,५,६,७,८,९,०

Nepali Typewriter



Keyboard Rules

Escape + key Combinations		
Key	Output	Comment
3	-	Hyphen
4	ऋ	Ri Vowel
5	ङ	Ri Matra
7	÷	Divide sign
8	×	Cross sign
½	-	Hyphen
»	--	Double Hyphen
I	ঁ	f Nukta
P	ঁ	Dh_Nukta
A	ঁ	kha Nukta
X	ঁ	ga Nukta
C	ঁ	ja Nukta
V	!	Exclamation Mark
B	*	Asterisk
M	ঁ	Da Nukta

Escape + Shift + key Combinations

Key	Output	Comment
Q	া	au Matra
O	ি	ii Vowel
P	়ে	Short e vowel
}	়ো	o vowel
!	!	Exclamation mark
@	@	Commercial at
#	#	Number sign
\$	\$	Dollar sign
%	%	Percent sign
^	^	Circumflex accent
&	&	Ampersand
*	*	Asterisk
('	Apostrophe
)	"	Quotation mark
-	-	Hyphen-minus
+	=	Equal sign

Escape + Control + key Combinations

Key	Output	Comment
,	়ু	uu vowel
]	়ৌ	au Vowel
[়া	aa vowel
1	1	One
2	2	Two
3	3	Three
4	4	Four
5	5	Five
6	6	Six
7	7	Seven
8	8	Eight
9	9	Nine
0	0	Zero
-		Null
=	+	Plus sign



Special Rules	
Vowel इ followed by repH generates vowel ई.	इ + RepH = ई
RepH is typed after a consonant/conjunct.	स + RepH = स्स
Half consonant followed by ओ matra will generate the full consonant.	ध + ओ = ध भ + ओ = भ ल + ओ = ल
1) ओ matra followed by ए matra will generate औ matra. 2) ओ matra followed by औ matra will generate औौ matra.	ए + ओ = औ का + ओ = को का + औौ = कौ
To type Roman Numerals (Numbers), use the Numpad Keys of the Keyboard with Caps Lock Key ON.	1, 2, 3,...,9,0.
To type Lingual Numerals (Numbers), use the Numpad Keys of the Keyboard with Caps Lock Key OFF.	१,२,३,४,५,६,७,८,९,०

Tool Setting Options

On-the-fly Help


Tool provides the simplest way to type text by using on-the-fly Help. As the user starts typing using transliteration keyboard, he can see the respective letters in selected Indian Language with various matra combinations.

To activate this feature select **On-the-Fly Help** from **Settings** Menu.




Show Keyboard

To view any keyboard (except Phonetic) select **Show Keyboard** option from **Settings** Menu.




Switch to English/Nepali

To switch to English Language, select **Switch to English** option from **Settings** Menu or use shortcut key Ctrl+Shift+T.




To switch to Punjabi Language again, select **Switch to Nepali** option from **Settings** Menu or use shortcut key Ctrl+Shift+T.



Help

To view help on Nepali Indic Input 2 tool, select **Help** from **Settings** Menu.




Troubleshooting

1. How can I make Language bar visible on my PC?

Right-click your Desktop taskbar, and point to **Toolbars**. See if **Language bar** selected, if not click on it to select. If Language bar is no longer listed in the toolbar menu try below steps:

VISTA/WINDOWS 7


- Go to **Control Panel > Regional and Language Options > Keyboards and Languages (tab) > Change Keyboards > Language Bar**
- Select radio button **Floating on Desktop** or **Docked in the taskbar**.
- Click **OK**.



2. How can I add Nepali Indic Input 2 on my Language bar?

VISTA/WINDOWS 7

- Go to **Control Panel > Regional and Language Options > Keyboards and Languages (tab) > Change Keyboards > General**.
- Click **Add** button, Select the Language (Nepali) and under Keyboard section check the box titled **Nepali Indic Input 2**.
- Click **OK**.



3. I do not want Nepali Indic Input 2 as the default input method for my PC. What can be done?

VISTA/WINDOWS 7

- Go to **Control Panel > Regional and Language Options > Keyboards and Languages (tab) > Change Keyboards > General**

Check both:

- ✓ You have not selected Nepali as your **Default Input Language**.
- ✓ You have not selected Nepali Indic Input 2 as an input method in Language bar.

To Uninstall Nepali Indic Input 2

Follow the steps below to uninstall the tool.

1. Open Windows **Control Panel** → **Add/Remove Programs** to remove the program(s).
2. Select **Nepali Indic Input 2** and click **Remove** button.
3. You will be prompted by a confirmatory message. Select **Yes** to remove the tool completely.

Note: It is recommended to close all running applications before uninstalling the Nepali Indic Input 2 Tool.